SIMPLY A FRINGED TRIANGLE SHAWL -a simple crochet pattern by francine toukou

SIMPLY A FRINGED TRIANGLE SHAWL

Simply series is a collection of structurally, very basic designs that were created for four simple purposes.

- To enable BEGINNERS to create aesthetically & functionally high-end designs that are simplistic in principle, with minimal skill requirements.
 To enable KNITTERS to cross over & easily access crochet in a clear. uncluttered, and uncomplicated format.
- 3. To take ADVANCED and INTERMEDIATE crocheters into a highly prolific space, by providing an arsenal of well designed, easy, go-to patterns.
- 4. To create a landscape where all 3 groups can learn foundational structures where the process has been pared down, enabling you to easily create your own designs & patterns based on these simplistic foundation and techniques.

YOU WILL NEED

690 yds of sport weight yarn in the color of your choice. Hook: 5.5 mm / I-9 or size needed to obtain gauge Yarn needle

13" wide / 33 cm piece of heavy card-board

FINISHED MEASUREMENTS

29" wide x 45" long / 74 cm x 114cm excluding fringe

STITCHES USED

- Chain (ch) - Half double crochet (hdc)

GAUGE

Take time to check your gauge.

10 hdc = 4" / 10cm

7 rows = 4" / 10cm

WRAP

Beginning at lower tip of with A, ch 5.

Row 1: 2 hdc in 4th ch from hook (skipped ch-3 counts as hdc, ch 1), ch 1, hdc in last ch (4 hdc).

Row 2: Ch 2, turn, hdc in space between first 2 sts, skip 2 center sts, 2 hdc in space between last hdc and beginning ch-4, hdc in 3rd ch of beginning ch-4.

Note; The last space in a row is the space between the last hdc and the beginning ch.

Row 3: Ch 2, turn, hdc in first space between sts, *skip 2 sts, 2 hdc in next space between sts; repeat across; hdc in top of beginning ch-2.

Repeat Row 3 until wrap is about 45" / 114.3 cm. Fasten off and weave in all ends.

FINISHING FRINGE

Wind yarn around 13" / 33 cm piece of heavy cardboard. Cut along one end of wraps to create stands about 22" / 56 cm long. Holding 5 strands together, fold strands in half. Using crochet hook pull the folded end through the end of a row at the edge of the wrap. Use the crochet hook to pull the cut ends through the fold. Repeat this process, working fringe in the end of each row along the entire lower edge of the shawl. Attach a fringe to the lower tip of the shawl. Trim the ends of the fringe to even.



The copyright of this pattern is held by Francine Toukou. The written instructions, photographs, designs and patterns are intended for the personal use of the reader, and may be reproduced for that purpose only. Commercial use is forbidden under law without written permission of the copyright holder.